

HPE0-S50^{Q&As}

Integrating HPE Synergy Solutions

Pass HP HPE0-S50 Exam with 100% Guarantee

Free Download Real Questions & Answers **PDF** and **VCE** file from:

<https://www.pass2lead.com/hpe0-s50.html>

100% Passing Guarantee
100% Money Back Assurance

Following Questions and Answers are all new published by HP Official Exam Center

-  **Instant Download** After Purchase
-  **100% Money Back** Guarantee
-  **365 Days** Free Update
-  **800,000+** Satisfied Customers



QUESTION 1

DRAG DROP

A customer needs a Synergy solution configuration with 40Gb uplinks that will connect to network equipment in a different rack.

Click and drag the cable type on the left to the corresponding distance between the frame and the network equipment on the right to meet the customer's needs.

Select and Place:

Transceiver/Cable Type	Distance Covered
QSFP+ MPO SR4 Transceiver	Between 5 and 15 meters
QSFP+ LC LR4 Transceiver	5 meters or less
QSFP+ DAC Cable	Between 300 meters and 10 km
QSFP+ Active Optical Cable	300 meters or less

Correct Answer:

Transceiver/Cable Type	Distance Covered	
	QSFP+ Active Optical Cable	Between 5 and 15 meters
	QSFP+ DAC Cable	5 meters or less
	QSFP+ LC LR4 Transceiver	Between 300 meters and 10 km
	QSFP+ MPO SR4 Transceiver	300 meters or less

QUESTION 2

A customer is unable to boot to a 3.5TB volume created and presented to a compute node.

What is likely preventing the boot?

- A. Boot volumes larger than 3TB are not supported on HPE Synergy.
- B. The system is set to Legacy BIOS mode instead of UEFI.
- C. The system is set to UEFI instead of Legacy BIOS mode.

D. Boot volumes larger than 2.2TB are not supported on Synergy.

Correct Answer: D

QUESTION 3

A customer has moved a USB bootable drive to another compute module but the compute module fails to boot from the USB device.

What should the Synergy integrator do to resolve this issue?

- A. In the server Profile, make sure OS Deployment is set to Deployment Plan.
- B. Use UEFI System Utilities to disable the B140i RAID controller.
- C. Verify that the USB drive key is enabled in UEFI System Utilities.
- D. Make sure PXE boot is disabled.

Correct Answer: B

QUESTION 4

A customer needs a consolidated infrastructure view for HPE Synergy and HPE BladeSystem c7000 enclosures. Which approach should the Synergy integrator take to meet the customer's needs?

- A. Enable federation in the HPE OneView appliance and add remote HPE OneView instances.
- B. Add remote enclosures to monitor the BladeSystem c7000 enclosures.
- C. Deploy HPE OneView Global Dashboard.
- D. Extend the Synergy out-of-band management ring to the c7000 Onboard Administrator ports.

Correct Answer: C

QUESTION 5

A customer has purchased 15 Synergy Frames with the following components:

150 HPE SY 480 compute modules

15 HPE Synergy D3940 storage modules with 40 disks each

6 Image Streamers

6 Virtual Connect SE 40Gb F8 modules

24 10Gb Interconnect Link Modules

How many frames can the configuration have for the Logical Enclosure?

A. 3 frames

B. 4 frames

C. 5 frames

D. 6 frames

Correct Answer: A

[HPE0-S50 Practice Test](#)

[HPE0-S50 Study Guide](#)

[HPE0-S50 Exam Questions](#)